



# Process of installing bar code driver

- 1、 double click,  and choose “I accept the terms in the license agreement” , click “Next” , as below picture:



- 2、 leave “Installation Directory” as default, go “Next” :



3、 Choose “Run Driver Wizard after unpacking drivers” and go “Next” .





4、 Choose “Install printer drivers” , click “Next” , as below picture:




5、 After installing the printer drivers , the printer automatic detects the communication USB port, go “Next” :


PS: No need to set port in driver if the program detected the communication port in this step.




6、 Default name of printer is “4BARCODE 3B-370BM” , Choose “Use this printer as the default printer” , click “Next” , as below picture:




7、 Completing driver installation, click “Finish” , as below picture:








8、 Complete the installation of driver “4BARCODE 3B-370BM” , click “Close” , As below picture:



9、After installed drivers, click “Start” → “All Programs” → “Devices and printers”, find “4BARCODE 3B-370BM”, Choose this icon, right click , “printer properties” , as below pictures:



10、 After the above steps are completed, click “general” → “print test page” 。



**The drive has been installed successfully when test page is printed. Thanks for your support**